

## Purpose

The purpose of this document is to provide details of the enhancements provided by APAR PI56881. These enhancements affect two areas.

- One provides the ability for the report specification archive definition exit (arsuupdt) to provide indexer parameters that will be appended to the end of the indexer parameters being passed to the indexer.
- The other enhancement is a means for the 390 indexer exits to indicate that an error has occurred, and that arslod should fail the load of the report.

## Report Specification Archive Definition

The high-level ArsCSXitUpdtExit structure in the arscsxit header file has had a field, AdditionalIndexerParms, added. The corresponding COBOL name in the arscsxic copybook is ArsCSXitUpdtExit-AddIndexer.

C definition:

```
typedef struct _ArsCSXitUpdtExit
{
    char                *pFileName;
    ArcI32              Function;
    char                ApplGrpName[ARCCSXIT_MAX_NAME_SIZE + 1];
    char                ApplName[ARCCSXIT_MAX_NAME_SIZE + 1];
    char                ObjServer[ARCCSXIT_MAX_SERVER_SIZE + 1];
    char                StorageNode[ARCCSXIT_MAX_NAME_SIZE + 1];
    void                *pJES;
    char                IndexerParms[ARCCSXIT_MAX_INDEXER_SIZE + 1];
    ArcCSXitCarCtl     CType;
    ArcI32              LRECL;
    ArcCSXitDocFormat  RECFM;
    ArcI32              UpdateAppl;
    char                Delim[ARCCSXIT_MAX_DELIMITER_SIZE + 1];
    char                *instance;
    char                DbFieldName[ARCCSXIT_MAX_DBCOL_NAME_SIZE + 1];
    char                DbFieldDateFormat[ARCCSXIT_MAX_DATEFMT_SIZE + 1];
    char                AdditionalIndexerParms[ARCCSXIT_MAX_INDEXER_SIZE + 1];
} ArsCSXitUpdtExit;
```

COBOL definition:

```
01  ArsCSXitUpdtExit.
    03  ArsCSXitUpdtExit-pFileName          pointer.
    03  ArsCSXitUpdtExit-Function          pic s9(9) comp.
        88  arccsxit-process-names        value 1.
        88  arccsxit-process-parms       value 2.
    03  ArsCSXitUpdtExit-ApplGrpName      pic x(61).
    03  ArsCSXitUpdtExit-ApplName        pic x(61).
    03  ArsCSXitUpdtExit-ObjServer       pic x(255).
    03  ArsCSXitUpdtExit-Node            pic x(61).
```



```

ARSUUPDA_AIXPRML DC    F'0'          U:  The true length
*                               (exclusive of the
*                               terminating null) of the
*                               Additional Indexer Parameters
*                               Parameters string.
*
ARSUUPDA_AIXPRMMXL DC    F'0'        I:  The maximum length of
*                               the string (exclusive of
*                               the terminating null)
*                               which can be placed in the
*                               area pointed to by the
*                               AIXPRMP field.

```

The ARSUUPDA (Assembler), ARSUUPDH (C) and ARSUUPDB (COBOL) SARSINST members have been updated for these new fields.

If you are using the sample ARSUUPDX or ARSUUPDZ programs, the samples must be re-assembled and linked in order to take advantage of the new ARSUUPDA\_AIXPRMP, ARSUUPDA\_AIXPRML, and ARSUUPDA\_AIXPRMMXL fields.

### 390 Indexer exits

Prior to PI56881, only the 390 Indexer ANYEXIT could return a status to indicate an error had occurred. The INPEXIT and INDXEXIT could not, and thus had no legitimate way to indicate that the load of the report should fail. As a consequence, sample exits shipped called abort(), which terminates the invoking program.

With PI56881, all three exits can return a status indicating that an error has occurred.

For the INPEXIT, the supplied ARSINPBK has been updated to provide a REC-ERROR to the existing RECORD-STATUS to indicate an error:

```

01 RECORD-STATUS          PIC X(3) .
   88 END-OF-FILE         VALUE 'EOF' .
   88 REC-ERROR           VALUE 'ERR' .

```

For the INPEXIT, the supplied ARSIN2BK has been updated to provide a ARSE2INP-ERR to the existing RECORD STATUS to indicate an error:

```

01 RECORD-STATUS          PIC X(3) .
   88 END-OF-FILE         VALUE 'EOF' .
   88 ARSE2INP-ERR       VALUE 'ERR' .

```

For the INDXEXIT, the supplied ARSINDBK has been updated to provide a WS-

IND-STATUS that contains WS-IND-ERR to indicate an error.

```
01  WS-IND-STATUS          PIC XXX.
    88  WS-IND-OK          VALUE '  '.
    88  WS-IND-ERR        VALUE 'ERR'.
```

When the INDXEXIT is called, the additional WS-IND-STATUS parameter is passed that can be used to indicate an error:

```
PROCEDURE DIVISION USING WS-HEADER-RECORD
                        WS-INDEX-NAME-COUNT-ORIGINAL
                        WS-INDEX-NAMES
                        WS-OS-LEVEL-FLAG
                        WS-EBCDIC-ASCII-SWITCH
                        WS-INDEXES-33
                        WS-IND-STATUS.
```

Regardless of which 390 indexer exit is called, if the exit sets the 'ERR' in the appropriate status , the load of the report will fail.

In addition, the sample 390 indexer exits have been updated to remove calls to abort(), and to instead set the 'ERR' status appropriately.