



**Program Directory for
IBM Enterprise COBOL VUE for z/OS**

V06.04.00

Program Number 5697-V61

FMIDs HADB640, JADB641, JADB642, JADB64H

for Use with
z/OS

Document Date: May 2022

GI13-4529-03

Note

Before using this information and the product it supports, be sure to read the general information under 8.0, "Notices" on page 29.

Contents

1.0 Introduction	1
1.1 Enterprise COBOL VUE Description	1
1.2 Enterprise COBOL FMIDs	2
2.0 Program Materials	3
2.1 Basic Machine-Readable Material	3
2.2 Optional Machine-Readable Material	4
2.3 Program Publications	4
2.3.1 Online documentation	4
2.3.2 PDF documentation	4
2.3.3 Optional Program Publications	5
2.4 Program Source Materials	5
2.5 Publications Useful During Installation	5
3.0 Program Support	6
3.1 Program Services	6
3.2 Preventive Service Planning	6
3.3 Statement of Support Procedures	7
4.0 Program and Service Level Information	8
4.1 Program Level Information	8
4.2 Service Level Information	9
5.0 Installation Requirements and Considerations	10
5.1 Driving System Requirements	10
5.1.1 Machine Requirements	10
5.1.2 Programming Requirements	10
5.2 Target System Requirements	11
5.2.1 Machine Requirements	11
5.2.2 Programming Requirements	12
5.2.2.1 Installation Requisites	12
5.2.2.2 Operational Requisites	12
5.2.2.3 Toleration/Coexistence Requisites	14
5.2.2.4 Incompatibility (Negative) Requisites	14
5.2.3 DASD Storage Requirements	14
5.3 FMIDs Deleted	16
5.4 Special Considerations	17
6.0 Installation Instructions	18
6.1 Installing Enterprise COBOL VUE	18
6.1.1 SMP/E Considerations for Installing Enterprise COBOL VUE	18
6.1.2 SMP/E Options Subentry Values	18

6.1.3	Sample Jobs	18
6.1.4	Run REPORT MISSINGFIX	20
6.1.5	Set up ISPF Editor Macro (Optional)	21
6.1.6	Allocate and Initialize the SMP/E CSI (Optional)	21
6.1.7	Perform SMP/E RECEIVE	21
6.1.8	Allocate SMP/E Target and Distribution Libraries	22
6.1.9	Allocate, create and mount ZFS Files (Optional)	22
6.1.10	Allocate File System Paths	23
6.1.11	Create DDDEF Entries	23
6.1.12	Perform SMP/E APPLY	23
6.1.13	Run the Installation Verification Programs	25
6.1.14	Perform SMP/E ACCEPT	25
6.2	Activating Enterprise COBOL VUE	26
6.2.1	Product Registration for Subcapacity Reporting Tool	26
6.2.2	Running Enterprise COBOL VUE from Unix System Services	27
6.2.3	Product Customization	27
7.0	Converting from Enterprise COBOL to Enterprise COBOL Value Unit Edition	28
8.0	Notices	29
8.1	Trademarks	29
	Reader's Comments	30

Figures

1.	Program File Content	3
2.	Basic Material	4
3.	Publications Useful During Installation	5
4.	PSP Upgrade and Subset ID	6
5.	Component IDs	7
6.	Driving System Software Requirements	11
7.	Target System Mandatory Installation Requisites	12
8.	Target System Mandatory Operational Requisites	12
9.	Total DASD Space Required by Enterprise COBOL VUE	14
10.	Storage Requirements for Enterprise COBOL VUE Target Libraries	16
11.	Enterprise COBOL VUE File System Paths	16
12.	Storage Requirements for Enterprise COBOL VUE Distribution Libraries	16
13.	SMP/E Options Subentry Values	18
14.	Sample Installation Jobs	19

1.0 Introduction

This program directory is intended for system programmers who are responsible for program installation and maintenance. It contains information about the material and procedures associated with the installation of IBM® Enterprise COBOL Value Unit Edition for z/OS®. This publication refers to IBM Enterprise COBOL Value Unit Edition for z/OS as Enterprise COBOL VUE.

The Program Directory contains the following sections:

- 2.0, “Program Materials” on page 3 identifies the basic program materials and documentation for Enterprise COBOL VUE.
- 3.0, “Program Support” on page 6 describes the IBM support available for Enterprise COBOL VUE.
- 4.0, “Program and Service Level Information” on page 8 lists the APARs (program level) and PTFs (service level) that have been incorporated into Enterprise COBOL VUE.
- 5.0, “Installation Requirements and Considerations” on page 10 identifies the resources and considerations that are required for installing and using Enterprise COBOL VUE.
- 6.0, “Installation Instructions” on page 18 provides detailed installation instructions for Enterprise COBOL VUE. It also describes the procedures for activating the functions of Enterprise COBOL VUE, or refers to appropriate publications.

Before installing Enterprise COBOL VUE, read the *CBPDO Memo To Users* and the *CBPDO Memo To Users Extension* that are supplied with this program in softcopy format and this program directory; then keep them for future reference. Section 3.2, “Preventive Service Planning” on page 6 tells you how to find any updates to the information and procedures in this program directory.

Enterprise COBOL VUE is supplied in a Custom-Built Product Delivery Offering (CBPDO, 5751-CS3). The program directory that is provided in softcopy format on the CBPDO tape is identical to the one included with your order. All service and HOLDDATA for Enterprise COBOL are included on the CBPDO tape.

Do not use this program directory if you install Enterprise COBOL VUE with a SystemPac or ServerPac. When you use one of those offerings, use the jobs and documentation supplied with the offering. The offering will point you to specific sections of this program directory as needed.

1.1 Enterprise COBOL VUE Description

Enterprise COBOL Value Unit Edition is the same as Enterprise COBOL for z/OS made available under a different Product Identifier (Product ID) and pricing metric. As such, it contains the same product functionality and uses the same FMIDs and COMPIDs. With the exception of the License Information document, other product publications are the same as those provided with Enterprise COBOL for z/OS (5655-EC6).

Enterprise COBOL Value Unit Edition provides the COBOL compiler with a one-time charge metric that is based on Value Units. The Value Unit price metric supports both full-capacity and sub-capacity environments. During installation, Enterprise COBOL Value Unit Edition must be registered so that it generates the correct SMF 89 Type 1 records for sub-capacity reporting (see section 6.2, “Activating Enterprise COBOL VUE” on page 26).

IBM Enterprise COBOL Value Unit Edition for z/OS is an advanced optimizing compiler that helps clients create and maintain COBOL applications that execute on IBM z/OS and take full advantage of the latest IBM Z[®] hardware features.

New capabilities in Enterprise COBOL Value Unit Edition for z/OS 6.4 include:

- Support of the latest IBM z/Architecture[®] to maximize your IBM z16[™] investment, reduce CPU usage, and improve performance of critical COBOL applications
- Improved Java[™]/COBOL interoperability to easily extend the capabilities of your COBOL programs with Java
- Interoperability between AMODE 31 (31-bit) and AMODE 64 (64-bit) COBOL programs to handle your growing COBOL program data without converting the entire application to run in AMODE 64
- Support for user-defined functions to enable you to write your own functions and invoke them like intrinsic functions, improving code modularity and maintainability
- Improved integration with IBM Automatic Binary Optimizer for z/OS to invest in your future so that modules you compile today take advantage of future IBM Z hardware enhancements, without having to be recompiled

1.2 Enterprise COBOL FMIDs

Enterprise COBOL consists of the following FMIDs:

HADB640
JADB641
JADB642
JADB64H

2.0 Program Materials

An IBM program is identified by a program number. The program number for Enterprise COBOL Value Unit Edition for z/OS is 5697-V61.

Basic Machine-Readable Materials are materials that are supplied under the base license and are required for the use of the product.

The program announcement material describes the features supported by Enterprise COBOL VUE. Ask your IBM representative for this information if you have not already received a copy.

2.1 Basic Machine-Readable Material

The distribution medium for this program is physical media or downloadable files. This program is in SMP/E RELFILE format and is installed by using SMP/E. See 6.0, "Installation Instructions" on page 18 for more information about how to install the program.

You can find information about the physical media for the basic machine-readable materials for Enterprise COBOL VUE in the *CBPDO Memo To Users Extension*.

Figure 1 describes the program file content for Enterprise COBOL VUE. You can refer to the *CBPDO Memo To Users Extension* to see where the files reside on the tape.

Notes:

1. The data set attributes in this table must be used in the JCL of jobs that read the data sets. However, because the data sets are in IEBCOPY unloaded format, their actual attributes might be different.
2. If any RELFILEs are identified as PDSEs, ensure that SMPTLIB data sets are allocated as PDSEs.

Figure 1 (Page 1 of 2). Program File Content

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.HADB640.F1	PDS	FB	80	8800
IBM.HADB640.F2	PDSE	U	0	6144
IBM.HADB640.F3	PDS	FB	80	8800
IBM.JADB641.F1	PDSE	U	0	6144
IBM.JADB641.F2	PDS	FB	80	8800

Figure 1 (Page 2 of 2). Program File Content

Name	OR G	R E C F M	L R E C L	BLK SIZE
IBM.JADB642.F1	PDSE	U	0	6144
IBM.JADB64H.F1	PDS	VB	255	27998

2.2 Optional Machine-Readable Material

No optional machine-readable materials are provided for Enterprise COBOL VUE.

2.3 Program Publications

The following sections identify the basic publications for Enterprise COBOL VUE. publications for Enterprise COBOL.

2.3.1 Online documentation

Online documentation is available in IBM Documentation (<https://www.ibm.com/docs/cobol-zos/6.4>).

2.3.2 PDF documentation

Documentation is provided for download in PDF from IBM Documentation. See PDF version documentation (<https://www.ibm.com/docs/cobol-zos/6.4?topic=pdf-version-documentation>) for details, or you can contact your IBM representative or IBM Business Partner.

Figure 2 (Page 1 of 2). Basic Material

Publication Title	Form Number	Media Format
License Information Document	GI13-4530-03	http://www.ibm.com/software/sla/sladb.nsf
Language Reference	SC27-8713-03	https://www.ibm.com/docs/cobol-zos/6.4
IBM Enterprise COBOL for z/OS Customization Guide	SC27-8712-03	https://www.ibm.com/docs/cobol-zos/6.4
Messages and Codes	SC27-4648-02	https://www.ibm.com/docs/cobol-zos/6.4
Migration Guide	GC27-8715-03	https://www.ibm.com/docs/cobol-zos/6.4
Performance Tuning Guide	SC27-9202-02	https://www.ibm.com/docs/cobol-zos/6.4
Programming Guide	SC27-8714-03	https://www.ibm.com/docs/cobol-zos/6.4

Figure 2 (Page 2 of 2). Basic Material

Publication Title	Form Number	Media Format
What's New	SC31-5708-00	https://www.ibm.com/docs/cobol-zos/6.4

2.3.3 Optional Program Publications

No optional publications are provided for Enterprise COBOL VUE.

2.4 Program Source Materials

No program source materials or viewable program listings are provided for Enterprise COBOL VUE.

2.5 Publications Useful During Installation

You might want to use the publications listed in Figure 3 during the installation of Enterprise COBOL VUE.

Figure 3. Publications Useful During Installation

Publication Title	Form Number	Media Format
<i>IBM SMP/E for z/OS User's Guide</i>	SA23-2277-02	https://www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zOSV2R5Library
<i>IBM SMP/E for z/OS Commands</i>	SA23-2275-05	https://www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zOSV2R5Library
<i>IBM SMP/E for z/OS Reference</i>	SA23-2276-02	https://www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zOSV2R5Library
<i>IBM SMP/E for z/OS Messages, Codes, and Diagnosis</i>	GA32-0883-04	https://www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zOSV2R5Library

3.0 Program Support

This section describes the IBM support available for Enterprise COBOL VUE.

3.1 Program Services

Contact your IBM representative for specific information about available program services.

3.2 Preventive Service Planning

Before you install Enterprise COBOL VUE, make sure that you have reviewed the current Preventive Service Planning (PSP) information. Review the PSP Bucket for General Information, Installation Documentation, and the Cross Product Dependencies sections. For the Recommended Service section, instead of reviewing the PSP Bucket, it is recommended you use the IBM.ProductInstall-RequiredService fix category in SMP/E to ensure you have all the recommended service installed. Use the **FIXCAT(IBM.ProductInstall-RequiredService)** operand on the **APPLY CHECK command**. See 6.1.12, “Perform SMP/E APPLY” on page 23 for a sample APPLY command.

If you obtained Enterprise COBOL VUE as part of a CBPDO, HOLDDATA is included.

If the CBPDO for Enterprise COBOL VUE is older than two weeks by the time you install the product materials, you can obtain the latest PSP Bucket information by going to the following website:

<http://www14.software.ibm.com/webapp/set2/psearch/search?domain=psp>

You can also use S/390 SoftwareXcel or contact the IBM Support Center to obtain the latest PSP Bucket information.

For program support, access the Software Support Website at <https://www.ibm.com/mysupport/s/>.

PSP Buckets are identified by UPGRADEs, which specify product levels; and SUBSETs, which specify the FMIDs for a product level. The UPGRADE and SUBSET values for Enterprise COBOL VUE are included in Figure 4.

Figure 4. PSP Upgrade and Subset ID

UPGRADE	SUBSET	Description
COBOLZOS640	HADB640	Enterprise COBOL Base
	JADB641	Enterprise COBOL US English
	JADB642	Enterprise COBOL Japanese
	JADB64H	Enterprise COBOL HFS

3.3 Statement of Support Procedures

For installation and technical support, open a new case or review already-opened cases at the IBM Support (<http://www.ibm.com/support>) website.

Conduct a search for known problems (<https://www.ibm.com/support/pages/mustgather-read-first-problems-encountered-enterprise-cobol-zos#searchforknownproblemshint>) before engaging support.

- IBM Business Partners should contact their local IBM office and field technical support specialist for technical marketing assistance.
- Business Partners can find installation and technical support from the IBM Support website.

Installation and technical support is also available from PartnerWorld Contact Services.

Support Line is also available for technical support.

Figure 5 identifies the component IDs (COMPID) for Enterprise COBOL VUE.

<i>Figure 5. Component IDs</i>			
FMID	COMPID	Component Name	RETAIN Release
HADB640	5655EC600	Enterprise COBOL Base	640
JADB641	5655EC600	Enterprise COBOL US English	641
JADB642	5655EC600	Enterprise COBOL Japanese	642
JADB64H	5655EC600	Enterprise COBOL HFS	64H

4.0 Program and Service Level Information

This section identifies the program and relevant service levels of Enterprise COBOL VUE. The program level refers to the APAR fixes that have been incorporated into the program. The service level refers to the PTFs that have been incorporated into the program.

4.1 Program Level Information

The following APAR fixes against Enterprise COBOL V06.03.00 have been incorporated into this release. They are listed by FMID.

- FMID HADB630

PH17022	PH22833	PH27539	PH34586	PH40356
PH18124	PH22936	PH27540	PH34804	PH40562
PH18205	PH23021	PH27558	PH35433	PH40668
PH18600	PH23097	PH29477	PH35434	PH40824
PH18638	PH23471	PH29539	PH35435	PH40825
PH18639	PH23527	PH29540	PH35436	PH40826
PH18640	PH23528	PH29541	PH35643	PH40827
PH18641	PH23529	PH29542	PH35652	PH40828
PH18765	PH23530	PH29543	PH36213	PH40876
PH18919	PH23531	PH29544	PH36669	PH41526
PH19228	PH23958	PH29714	PH37039	PH41632
PH19229	PH24343	PH29848	PH37185	PH41682
PH19230	PH24829	PH30678	PH37213	PH41808
PH19231	PH25221	PH30975	PH37328	PH41810
PH19232	PH25222	PH31045	PH37330	PH41863
PH19233	PH25224	PH31047	PH37331	PH41920
PH19234	PH25225	PH31333	PH37332	PH41963
PH20724	PH25226	PH31467	PH37333	PH42022
PH20991	PH25272	PH31468	PH37709	PH42023
PH20994	PH25371	PH31470	PH38148	PH42040
PH20995	PH26709	PH31471	PH38499	PH42041
PH20997	PH26789	PH31472	PH38503	PH42280
PH20998	PH27504	PH31972	PH39230	PH42514
PH20999	PH27531	PH33122	PH39252	PH43128
PH21000	PH27532	PH33224	PH39253	PH43221
PH21007	PH27534	PH33458	PH39254	PH43250
PH22063	PH27535	PH33664	PH39904	PH43340
PH22114	PH27536	PH33665	PH40311	PH44305
PH22581	PH27537	PH33666	PH40314	PH44900
PH22646	PH27538			

4.2 Service Level Information

No PTFs against this release of Enterprise COBOL VUE have been incorporated into the product package.

Frequently check the Enterprise COBOL PSP Bucket for HIPER and SPECIAL attention PTFs against all FMIDs that you must install. You can also receive the latest HOLDDATA, then add the

FIXCAT(IBM.TargetSystem-RequiredService.Enterprise-COBOL.*)

operand on your APPLY CHECK command. This will allow you to review the recommended and critical service that should be installed with your FMIDs.

5.0 Installation Requirements and Considerations

The following sections identify the system requirements for installing and activating Enterprise COBOL VUE. The following terminology is used:

- *Driving system*: the system on which SMP/E is executed to install the program.
The program might have specific operating system or product level requirements for using processes, such as binder or assembly utilities during the installation.
- *Target system*: the system on which the program is configured and run.
The program might have specific product level requirements, such as needing access to the library of another product for link-edits. These requirements, either mandatory or optional, might directly affect the element during the installation or in its basic or enhanced operation.

In many cases, you can use a system as both a driving system and a target system. However, you can make a separate IPL-able clone of the running system to use as a target system. The clone must include copies of all system libraries that SMP/E updates, copies of the SMP/E CSI data sets that describe the system libraries, and your PARMLIB and PROCLIB.

Use separate driving and target systems in the following situations:

- When you install a new level of a product that is already installed, the new level of the product will replace the old one. By installing the new level onto a separate target system, you can test the new level and keep the old one in production at the same time.
- When you install a product that shares libraries or load modules with other products, the installation can disrupt the other products. By installing the product onto a separate target system, you can assess these impacts without disrupting your production system.

5.1 Driving System Requirements

This section describes the environment of the driving system required to install Enterprise COBOL VUE.

5.1.1 Machine Requirements

The driving system can run in any hardware environment that supports the required software.

5.1.2 Programming Requirements

Figure 6. Driving System Software Requirements

Program Number	Product Name	Minimum VRM	Minimum Service Level will satisfy these APARs	Included in the shipped product?
5650-ZOS	z/OS	V02.03.00 or higher	N/A	No

Note: SMP/E is a requirement for Installation and is an element of z/OS but can also be ordered as a separate product, 5655-G44, minimally V03.06.00.

Note: Installation might require migration to new z/OS releases to be service supported. See http://www.ibm.com/systems/z/os/zos/support/zos_eos_dates.html.

If you plan on installing the Japanese FMID JADB642 then ensure you have codepage 939 which is the Latin-based Japanese codepage that displays both upper and lower case characters correctly. Mixed case character usage is required for the sample IGYWDDEF, IGYWZFS, and IGYISMKD jobs; therefore, codepage 939 is required to run these jobs from the driving system.

Enterprise COBOL VUE is installed into a file system, either HFS or zFS. Before installing Enterprise COBOL VUE, you must ensure that the target system file system data sets are available for processing on the driving system. OMVS must be active on the driving system and the target system file data sets must be mounted on the driving system.

If you plan to install Enterprise COBOL VUE in a zFS file system, this requires that zFS be active on the driving system. Information on activating and using zFS can be found in z/OS Distributed File Service zSeries File System Administration, SC24-5989.

5.2 Target System Requirements

This section describes the environment of the target system required to install and use Enterprise COBOL VUE.

Enterprise COBOL VUE installs in the z/OS (Z038) SREL.

5.2.1 Machine Requirements

Enterprise COBOL VUE V06.04.00 will run on the following IBM System z servers:

- IBM z16
- IBM z15™ Models T01 and T02
- IBM z14® Models M01-M05
- IBM z14 Model ZR1
- IBM z13®

- IBM z13s®
- IBM zEnterprise® EC12
- IBM zEnterprise BC12

5.2.2 Programming Requirements

5.2.2.1 Installation Requisites: Installation requisites identify products that are required and *must* be present on the system or products that are not required but *should* be present on the system for the successful installation of this product.

Mandatory installation requisites identify products that are required on the system for the successful installation of this product.

<i>Figure 7. Target System Mandatory Installation Requisites</i>				
Program Number	Product Name	Minimum VRM	Minimum Service Level will satisfy these APARs	Included in the shipped product?
5650-ZOS	z/OS	V02.03.00 or higher	N/A	No

Note: Installation might require migration to new z/OS releases to be service supported. See http://www.ibm.com/systems/z/os/zos/support/zos_eos_dates.html.

Conditional installation requisites identify products that are *not* required for successful installation of this product but can resolve such things as certain warning messages at installation time.

Enterprise COBOL VUE has no conditional installation requisites.

5.2.2.2 Operational Requisites: Operational requisites are products that are required and *must* be present on the system or products that are not required but *should* be present on the system for this product to operate all or part of its functions.

Mandatory operational requisites identify products that are required for this product to operate its basic functions.

<i>Figure 8 (Page 1 of 2). Target System Mandatory Operational Requisites</i>		
Program Number	Product Name and Minimum VRM/Service Level	Function
5650-ZOS	z/OS V02.03.00 or higher	z/OS Language Environment® and Program Management, required to compile and run COBOL applications

Figure 8 (Page 2 of 2). Target System Mandatory Operational Requisites

Program Number	Product Name and Minimum VRM/Service Level	Function
5650-ZOS	Language Environment for z/OS V2R3 with the PTFs for APARs PH28966, PH07107, PH09543, PH45656 and PH45659 applied	PH28966 provides AMODE 31 and AMODE 64 programs interoperability support PH07107 CEEMKDIR REXX PH09543 LLVM and header files PH45656 COBOL run-time (AMODE31) PH45659 COBOL run-time (AMODE64)
	Language Environment for z/OS V2R4 with the PTFs for APARs PH28966, PH45656 and PH45659 applied	PH28966 provides AMODE 31 and AMODE 64 programs interoperability support PH45656 COBOL run-time (AMODE31) PH45659 COBOL run-time (AMODE64)
	Language Environment for z/OS V2R5 with the PTFs for APARs PH45656 and PH45659 applied	PH45656 COBOL run-time (AMODE31) PH45659 COBOL run-time (AMODE64)
5655-DGH, 5655-DGG, 5655-DGJ	IBM SDK for z/OS, Java Technology Edition 8.0.6.36 (JVM), IBM Seremu Certified Edition for z/OS, V11.0.14.1, or later	Required for COBOL/Java interoperability feature.
5650-ZOS	z/OS XML System Services 2.3, or later.	Required for Enterprise COBOL XML PARSE statements in programs, which are compiled with the XMLPARSE(XMLSS) compiler option.
5650-ZOS	z/OS High Level Assembler	Required for customization during or after installation.

Note:

Depending on the target system that you are running, ensure that the appropriate level of LE PTF(s) for the following APAR has been installed on your system.

- PH28966, PH07107, PH09543, PH45656 and PH45959 (z/OS V2R3 Language Environment)
- PH28966, PH45656 and PH45959 (z/OS V2R4 Language Environment)
- PH45656 and PH45959 (z/OS V2R5 Language Environment)

Conditional operational requisites identify products that are *not* required for this product to operate its basic functions but are required at run time for this product to operate specific functions.

Target System Conditional Operational Requisites

You may need various other products (eg. Db2®, CICS® or IMS) depending on the Enterprise COBOL function you are using. Please check the Software Product Compatibility Reports (SPCR) at <https://www.ibm.com/software/reports/compatibility/clarity/index.html> for a list of compatible software. From

the SPCR home page, click Create a report under In-depth reports, search for Enterprise COBOL for z/OS and choose Version 6.4, and then click Submit.

5.2.2.3 Toleration/Coexistence Requisites: Toleration/coexistence requisites identify products that must be present on sharing systems. These systems can be other systems in a multisystem environment (not necessarily sysplex), a shared DASD environment (such as test and production), or systems that reuse the same DASD environment at different time intervals.

Enterprise COBOL VUE has no toleration/coexistence requisites.

5.2.2.4 Incompatibility (Negative) Requisites: Negative requisites identify products that must *not* be installed on the same system as this product.

Enterprise COBOL has no incompatibility requisites.

5.2.3 DASD Storage Requirements

Enterprise COBOL VUE libraries can reside on all supported DASD types.

Figure 9 lists the total space that is required for each type of library.

Library Type	Total Space Required in 3390 Trks
Target	2582
Distribution	2555
File System	30

Notes:

1. For non-RECFM U data sets, IBM recommends using system-determined block sizes for efficient DASD utilization. For RECFM U data sets, IBM recommends using a block size of 32760, which is most efficient from the performance and DASD utilization perspective.
2. Abbreviations used for data set types are shown as follows.
 - U** Unique data set, allocated by this product and used by only this product. This table provides all the required information to determine the correct storage for this data set. You do not need to refer to other tables or program directories for the data set size.
 - S** Shared data set, allocated by this product and used by this product and other products. To determine the correct storage needed for this data set, add the storage size given in this table to those given in other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.

- E** Existing shared data set, used by this product and other products. This data set is *not* allocated by this product. To determine the correct storage for this data set, add the storage size given in this table to those given in other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.

If you currently have a previous release of this product installed in these libraries, the installation of this release will delete the old release and reclaim the space that was used by the old release and any service that had been installed. You can determine whether these libraries have enough space by deleting the old release with a dummy function, compressing the libraries, and comparing the space requirements with the free space in the libraries.

For more information about the names and sizes of the required data sets, see 6.1.8, “Allocate SMP/E Target and Distribution Libraries” on page 22.

3. Abbreviations used for the file system path type are as follows.

- N** New path, created by this product.
X Path created by this product, but might already exist from a previous release.
P Previously existing path, created by another product.

4. All target and distribution libraries listed have the following attributes:

- The default name of the data set can be changed.
- The default block size of the data set can be changed.
- The data set can be merged with another data set that has equivalent characteristics.
- The data set can be either a PDS or a PDSE, except for SIGYCOMP and AIGYMOD1, which must be PDSEs.

5. All target libraries listed have the following attributes:

- These data sets can be SMS-managed, but they are not required to be SMS-managed.
- These data sets are not required to reside on the IPL volume.
- The values in the "Member Type" column are not necessarily the actual SMP/E element types that are identified in the SMPMCS.

6. All target libraries that are listed and contain load modules have the following attributes:

- These data sets can be in the LPA, but they are not required to be in the LPA.
- These data sets can be in the LNKLIST.
- These data sets are not required to be APF-authorized.
- Enterprise COBOL VUE requires that the SMPLTS data set must be a PDSE. If your existing SMPLTS is a PDS, you will need to allocate a new PDSE and copy your existing SMPLTS into it and then change the SMPLTS DDDEF entry to indicate the new PDSE data set.

The following figures describe the target and distribution libraries and file system paths required to install Enterprise COBOL VUE. The storage requirements of Enterprise COBOL VUE must be added to the storage required by other programs that have data in the same library or path.

Note: Use the data in these tables to determine which libraries can be merged into common data sets. In addition, since some ALIAS names may not be unique, ensure that no naming conflicts will be introduced before merging libraries.

Figure 10. Storage Requirements for Enterprise COBOL VUE Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SIGYCOMP	LMOD	ANY	U	PDSE	U	0	2500	n/a
SIGYMAC	MACRO	ANY	U	PDS	FB	80	10	5
SIGYPROC	PROC	ANY	U	PDS	FB	80	2	5
SIGYSAMP	SAMP	ANY	U	PDS	FB	80	35	10
SIGYLIB	SAMP	ANY	U	PDS	FB	80	35	10

Figure 11. Enterprise COBOL VUE File System Paths

DDNAME	T Y P E	Path Name
SIGYHFS	N	/usr/lpp/IBM/cobol/igyv6r4/bin/IBM

Figure 12. Storage Requirements for Enterprise COBOL VUE Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
AIGYHFS	U	PDS	VB	255	10	5
AIGYMOD1	U	PDSE	U	0	2500	n/a
AIGYSRC1	U	PDS	FB	80	45	12

5.3 FMIDs Deleted

Installing Enterprise COBOL VUE might result in the deletion of other FMIDs. To see which FMIDs will be deleted, examine the ++VER statement in the SMPMCS of the product.

If you do not want to delete these FMIDs at this time, install Enterprise COBOL VUE into separate SMP/E target and distribution zones.

Note: These FMIDs are not automatically deleted from the Global Zone. If you want to delete these FMIDs from the Global Zone, use the SMP/E REJECT NOFMID DELETEFMID command. See the SMP/E Commands book for details.

5.4 Special Considerations

PDSE Considerations:

Enterprise COBOL VUE uses the "partitioned data set extended" or PDSE format for the SIGYCOMP target library. There are some operational differences between PDS and PDSE data sets. The PDS format may be shared by more than one z/OS system and no special precautions are necessary. However, the PDSE format may only be shared by z/OS systems which are part of a sysplex or which are connected using Global Resource Serialization (are in a GRS complex). If z/OS systems share use of a PDSE data set outside of a sysplex or GRS environment, you may experience severe problems when the data set is updated. This is due to the fact that PDSE directory information is cached in storage, and when the data set is updated from one system, but the other system(s) have no knowledge of the update, and their cached directory information will be incorrect.

You must take care not to share the SIGYCOMP data set between z/OS systems unless they are in a sysplex or are connected in a GRS complex. If you need to share the content of the SIGYCOMP data set, a separate copy must be created for each z/OS system.

6.0 Installation Instructions

This chapter describes the installation method and the step-by-step procedures to install and to activate the functions of Enterprise COBOL VUE.

Please note the following points:

- You can use the sample jobs that are provided to perform part or all of the installation tasks. The SMP/E jobs assume that all DDDEF entries that are required for SMP/E execution have been defined in appropriate zones.
- You can use the SMP/E dialogs instead of the sample jobs to accomplish the SMP/E installation steps.

6.1 Installing Enterprise COBOL VUE

6.1.1 SMP/E Considerations for Installing Enterprise COBOL VUE

Use the SMP/E RECEIVE, APPLY, and ACCEPT commands to install this release of Enterprise COBOL VUE.

6.1.2 SMP/E Options Subentry Values

The recommended values for certain SMP/E CSI subentries are shown in Figure 13. Using values lower than the recommended values can result in failures in the installation. DSSPACE is a subentry in the GLOBAL options entry. PEMAX is a subentry of the GENERAL entry in the GLOBAL options entry. See the SMP/E manuals for instructions on updating the global zone.

Figure 13. SMP/E Options Subentry Values

Subentry	Value	Comment
DSSPACE	(500,500,500)	3390 DASD tracks
PEMAX	SMP/E Default	IBM recommends using the SMP/E default for PEMAX.

6.1.3 Sample Jobs

The following sample installation jobs are provided as part of the product to help you install Enterprise COBOL VUE:

Figure 14. Sample Installation Jobs

Job Name	Job Type	Description	RELFILE
IGYWEDIT	MACRO	ISPF editor macro to aid users in making changes to the sample jobs (Optional)	IBM.HADB640.F3
IGYWSMPE	SMP/E	Sample job to define and prime a new SMP/E CSI (Optional)	IBM.HADB640.F3
IGYWRECV	RECEIVE	Sample RECEIVE job	IBM.HADB640.F3
IGYWALOC	ALLOCATE	Sample job to allocate target and distribution libraries	IBM.HADB640.F3
IGYWZFS	ALLOMZFS	Sample job to allocate, create mountpoint, & mount zFS data sets (Optional)	IBM.HADB640.F3
IGYISMKD	MKDIR	Sample job to invoke the supplied IGYMKDIR EXEC to allocate file system paths	IBM.HADB640.F3
IGYWDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.HADB640.F3
IGYWAPLY	APPLY	Sample APPLY job	IBM.HADB640.F3
IGYWIVP1	IVP	Sample job to verify installation has been successful	IBM.HADB640.F3
IGYWIVP2	IVP	Sample job to verify installation has been successful	IBM.HADB640.F3
IGYWACPT	ACCEPT	Sample ACCEPT job	IBM.HADB640.F3

You can access the sample installation jobs by performing an SMP/E RECEIVE (refer to 6.1.7, “Perform SMP/E RECEIVE” on page 21), and then copy the jobs from the RELFILES to a work data set for editing and submission. See Figure 14 on page 18 to find the appropriate relfile data set.

You can also copy the sample installation jobs from the tape or product files by submitting the following job. Depending on your distribution medium, use either the //TAPEIN or the //FILEIN DD statement and comment out or delete the other statement. Before you submit the job, add a job card and change the lowercase parameters to uppercase values to meet the requirements of your site.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//*****
/* Make the //TAPEIN DD statement below active if you install*
/* from a CBPDO tape by uncommenting the DD statement below. *
//*****
/*TAPEIN DD DSN=IBM.HADB640.F3,UNIT=tunit,
/* VOL=SER=volser,LABEL=(x,SL),
/* DISP=(OLD,KEEP)
//*****
/* Make the //TAPEIN DD statement below active if you install*
/* from a product tape received outside the CBPDO process *
/* (using the optional SMP/E RECEIVE job) by uncommenting *
```

```

/* the DD statement below.
/******
/*TAPEIN DD DSN=IBM.HADB640.F3,UNIT=tunit,
/* VOL=SER=ADB640,LABEL=(4,SL),
/* DISP=(OLD,KEEP)
/******
/* Make the //FILEIN DD statement below active for
/* downloaded DASD files.
/******
/*FILEIN DD DSN=IBM.HADB640.F3,UNIT=SYSALLDA,DISP=SHR,
/* VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,
// DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,
// SPACE=(TRK,(20,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=xxxxIN,OUTDD=OUT
SELECT MEMBER=(IGYISMKD,IGYWACPT,IGYWALOC,IGYWAPLY)
SELECT MEMBER=(IGYWDEF,IGYWEDIT,IGYWIVP1,IGYWIVP2)
SELECT MEMBER=(IGYWRECV,IGYWSMPE,IGYWZFS)
/*

```

See the following information to update the statements in the previous sample:

TAPEIN:

- tunit** is the unit value that matches the product package.
- volser** is the volume serial that matches the product package.
- x** is the tape file number that indicates the location of the data set name on the tape.
- See the documentation that is provided by CBPDO for the location of IBM.HADB640.F3 on the tape.

FILEIN:

- filevol** is the volume serial of the DASD device where the downloaded files reside.

OUT:

- jcl-library-name** is the name of the output data set where the sample jobs are stored.
- dasdvol** is the volume serial of the DASD device where the output data set resides.

SYSIN:

- xxxxIN** is either TAPEIN or FILEIN depending on your input DD statement.

6.1.4 Run REPORT MISSINGFIX

The SMP/E REPORT MISSINGFIX command helps you determine whether any FIXCAT APARs exist that are applicable and have not yet been installed.

Before you install Enterprise COBOL VUE, it is recommended that you run REPORT MISSINGFIX. This requires a global zone with ZONEINDEX entries that describe all the target and distribution libraries to be reported on, the SET BOUNDARY command must specify the global zone.

Here is a sample REPORT MISSINGFIX command to run against your z/OS CSI, (include previous versions):

```
SET BDY(globalzone).  
REPORT MISSINGFIX ZONES(targetzone)  
FIXCAT(IBM.TargetSystem-RequiredService.Enterprise-COBOL.*)
```

For more information about REPORT MISSINGFIX, see the SMP/E manuals.

6.1.5 Set up ISPF Editor Macro (Optional)

To aid you in making changes to the SMP/E installation jobs (IGYISMKD, IGYWACPT, IGYWALOC, IGYWAPLY, IGYWDDEF, IGYWIVP1, IGYWIVP2, IGYWRECV, IGYWSMPE, and IGYWZFS), an ISPF editor macro, called IGYWEDIT, is supplied and is copied to your output data set **jcl-library-name** above. (See Figure 14 on page 18).

This macro lets you substitute proper values for all of the required variables in those jobs instead of making the changes repeatedly by hand.

Edit macro IGYWEDIT and provide the proper values, then copy it to any data set in your TSO logon procedure SYSEXEC concatenation. Consult the instructions in the macro for more information.

6.1.6 Allocate and Initialize the SMP/E CSI (Optional)

If you are using an existing CSI do not execute this job.

If you install into existing SMP/E data sets, make sure that you have enough space.

If you plan to install into an existing zone, the cluster should already have been allocated and primed. You can go on to the next step to perform a SMP/E RECEIVE.

To install into a new zone, use the IGYWSMPE sample job to allocate and prime the SMPCSI cluster. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.7 Perform SMP/E RECEIVE

If you have obtained Enterprise COBOL VUE as part of a CBPDO, use the RCVPDO job in the CBPDO RIMLIB data set to receive the Enterprise COBOL VUE FMIDs, service, and HOLDDATA that are included on the CBPDO package. For more information, see the documentation that is included in the CBPDO.

You can also choose to edit and submit sample job IGYWRECV to perform the SMP/E RECEIVE for Enterprise COBOL VUE. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.8 Allocate SMP/E Target and Distribution Libraries

Edit and submit sample job IGYWALOC to allocate the SMP/E target and distribution libraries for Enterprise COBOL VUE. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.9 Allocate, create and mount ZFS Files (Optional)

This job allocates, creates a mountpoint, and mounts zFS data sets.

If you plan to install Enterprise COBOL VUE into a new z/OS UNIX file system, you can edit and submit the optional IGYWZFS job to perform the following tasks:

- Create the z/OS UNIX file system
- Create a mount point
- Mount the z/OS UNIX file system on the mountpoint

Consult the instructions in the sample job for more information.

The recommended z/OS UNIX file system type is *zFS*. The recommended mount point is */usr/lpp/IBM/cobol/igyv6r4*.

Before running the sample job to create the z/OS UNIX file system, you must ensure that OMVS is active on the driving system. zFS must be active on the driving system if you are installing Enterprise COBOL VUE into a file system that is zFS.

If you create a new file system for this product, consider updating the BPXPRMxx PARMLIB member to mount the new file system at IPL time. This action can be helpful if an IPL occurs before the installation is completed.

```
MOUNT FILESYSTEM('#dsn')
MOUNTPOINT('/usr/lpp/IBM/cobol/igyv6r4')
MODE(RDWR) /* can be MODE(READ) */
TYPE(ZFS) PARM('AGGRGROW') /* zFS, with extents */
```

See the following information to update the statements in the previous sample:

- **#dsn** is the name of the data set holding the z/OS UNIX file system.
- **/usr/lpp/IBM/cobol/igyv6r4** is the name of the mount point where the z/OS UNIX file system will be mounted.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.10 Allocate File System Paths

The target system HFS or zFS data set must be mounted on the driving system when running the sample IGYISMKD job since the job will create paths in the HFS or zFS.

Before running the sample job to create the paths in the file system, you must ensure that OMVS is active on the driving system and that the target system's HFS or zFS file system is mounted to the driving system. zFS must be active on the driving system if you are installing Enterprise COBOL VUE into a file system that is zFS.

If you plan to install Enterprise COBOL VUE into a new HFS or zFS file system, you must create the mountpoint and mount the new file system to the driving system for Enterprise COBOL VUE.

The recommended mountpoint is `/usr/lpp/IBM/cobol/igyv6r4`.

Edit and submit sample job IGYISMKD to allocate the HFS or zFS paths for Enterprise COBOL VUE. Consult the instructions in the sample job for more information.

If you create a new file system for this product, consider updating the BPXPRMxx PARMLIB member to mount the new file system at IPL time. This action can be helpful if an IPL occurs before the installation is completed.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.11 Create DDDEF Entries

Edit and submit sample job IGYWDDEF to create DDDEF entries for the SMP/E target and distribution libraries for Enterprise COBOL VUE. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.12 Perform SMP/E APPLY

1. Ensure that you have the latest HOLDDATA; then edit and submit sample job IGYWAPLY to perform an SMP/E APPLY CHECK for Enterprise COBOL VUE. Consult the instructions in the sample job for more information.

The latest HOLDDATA is available through several different portals, including <http://service.software.ibm.com/holdata/390holddata.html>. The latest HOLDDATA may identify HIPER and FIXCAT APARs for the FMIDs you will be installing. An APPLY CHECK will help you determine if any HIPER or FIXCAT APARs are applicable to the FMIDs you are installing. If there are any applicable HIPER or FIXCAT APARs, the APPLY CHECK will also identify fixing PTFs that will resolve the APARs, if a fixing PTF is available.

You should install the FMIDs regardless of the status of unresolved HIPER or FIXCAT APARs. However, do not deploy the software until the unresolved HIPER and FIXCAT APARs have been analyzed to determine their applicability. That is, before deploying the software either ensure fixing

PTFs are applied to resolve all HIPER or FIXCAT APARs, or ensure the problems reported by all HIPER or FIXCAT APARs are not applicable to your environment.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the PRE, ID, REQ, and IFREQ on the APPLY CHECK. The SMP/E root cause analysis identifies the cause only of *errors* and not of *warnings* (SMP/E treats bypassed PRE, ID, REQ, and IFREQ conditions as warnings, instead of errors).

Here are sample APPLY commands:

- a. To ensure that all recommended and critical service is installed with the FMIDs, receive the latest HOLDDATA and use the APPLY CHECK command as follows

```
APPLY S(fmid,fmid,...) CHECK
FORFMID(fmid,fmid,...)
SOURCEID(RSU*)
FIXCAT(IBM.ProductInstall-RequiredService)
FIXCAT(IBM.TargetSystem-RequiredService.Enterprise-COBOL.V6R4)
GROUPEXTEND .
```

Some HIPER APARs might not have fixing PTFs available yet. You should analyze the symptom flags for the unresolved HIPER APARs to determine if the reported problem is applicable to your environment and if you should bypass the specific ERROR HOLDS in order to continue the installation of the FMIDs.

This method requires more initial research, but can provide resolution for all HIPERs that have fixing PTFs available and are not in a PE chain. Unresolved PEs or HIPERs might still exist and require the use of BYPASS.

- b. To install the FMIDs without regard for unresolved HIPER APARs, you can add the BYPASS(HOLDCLASS(HIPER)) operand to the APPLY CHECK command. This will allow you to install FMIDs even though one or more unresolved HIPER APARs exist. After the FMIDs are installed, use the SMP/E REPORT ERRSYSMODS command to identify unresolved HIPER APARs and any fixing PTFs.

```
APPLY S(fmid,fmid,...) CHECK
FORFMID(fmid,fmid,...)
SOURCEID(RSU*)
FIXCAT(IBM.ProductInstall-RequiredService)
FIXCAT(IBM.TargetSystem-RequiredService.Enterprise-COBOL.V6R4)
GROUPEXTEND
BYPASS(HOLDCLASS(HIPER),HOLDFIXCAT) .
..any other parameters documented in the program directory
```

This method is quicker, but requires subsequent review of the Exception SYSMOD report produced by the REPORT ERRSYSMODS command to investigate any unresolved HIPERs. If you have received the latest HOLDDATA, you can also choose to use the REPORT MISSINGFIX command and specify Fix Category IBM.ProductInstall-RequiredService to investigate missing recommended service.

It is recommended that you run REPORT MISSINGFIX specifying your COBOL category against OTHER target zones, to identify required PTFs that are missing from those other target zones.

This is particularly important if COBOL is installed in a target zone different to LE (refer to 6.1.4, “Run REPORT MISSINGFIX” on page 20).

If you bypass HOLDS during the installation of the FMIDs because fixing PTFs are not yet available, you can be notified when the fixing PTFs are available by using the APAR Status Tracking (AST) function of ServiceLink or the APAR Tracking function of ResourceLink.

2. After you take actions that are indicated by the APPLY CHECK, remove the CHECK operand and run the job again to perform the APPLY.

Note: The GROUPEXTEND operand indicates that SMP/E applies all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from APPLY CHECK: You will receive a return code of 0 if this job runs correctly.

Expected Return Codes and Messages from APPLY: You will receive a return code of 0 if this job runs correctly.

6.1.13 Run the Installation Verification Programs

Make sure you have applied the PTFs for the Language Environment and Program Management APARs listed in Figure 8 on page 12, then edit and submit sample jobs IGYWIVP1 and IGYWIVP2 to verify that you have installed Enterprise COBOL VUE correctly. Refer to the instructions in the sample jobs for more information and expected output.

Expected Return Codes and Messages: You will receive return codes of 0 if these jobs run correctly.

Note: If operational requisite PTFs for the Language Environment have not already been applied, the IGYWIVP1 sample job will fail at LINK step. You will receive abend code of RC=0008 and message:

```
IEW2456E 9207 SYMBOL IGZXLERR UNRESOLVED. MEMBER COULD NOT BE INCLUDED FROM  
THE DESIGNATED CALL LIBRARY.
```

6.1.14 Perform SMP/E ACCEPT

Edit and submit sample job IGYWACPT to perform an SMP/E ACCEPT CHECK for Enterprise COBOL VUE. Consult the instructions in the sample job for more information.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the PRE, ID, REQ, and IFREQ on the ACCEPT CHECK. The SMP/E root cause analysis identifies the cause of *errors* but not *warnings* (SMP/E treats bypassed PRE, ID, REQ, and IFREQ conditions as warnings rather than errors).

Before you use SMP/E to load new distribution libraries, it is recommended that you set the ACCJCLIN indicator in the distribution zone. In this way, you can save the entries that are produced from JCLIN in the distribution zone whenever a SYSMOD that contains inline JCLIN is accepted. For more information about the ACCJCLIN indicator, see the description of inline JCLIN in the SMP/E Commands book for details.

After you take actions that are indicated by the ACCEPT CHECK, remove the CHECK operand and run the job again to perform the ACCEPT.

Note: The GROUPEXTEND operand indicates that SMP/E accepts all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from ACCEPT CHECK: You will receive a return code of 0 if this job runs correctly.

If PTFs that contain replacement modules are accepted, SMP/E ACCEPT processing will link-edit or bind the modules into the distribution libraries. During this processing, the Linkage Editor or Binder might issue messages that indicate unresolved external references, which will result in a return code of 4 during the ACCEPT phase. You can ignore these messages, because the distribution libraries are not executable and the unresolved external references do not affect the executable system libraries.

Expected Return Codes and Messages from ACCEPT: You will receive a return code of 0 if this job runs correctly.

6.2 Activating Enterprise COBOL VUE

6.2.1 Product Registration for Subcapacity Reporting Tool

Enterprise COBOL Value Unit Edition must be registered in order for the compiler to generate the correct SMF 89 Type 1 records for Subcapacity Reporting.

Parmlib member IFAPRDxx needs to be updated to include a PRODUCT entry as follows:

```
PRODUCT OWNER('IBM CORP')
NAME('IBM COBOL VUE')
ID(5697-V61)
VERSION(*) RELEASE(*) MOD(*)
FEATURENAME('COBOL-COMPLR-VUE')
STATE(ENABLED)
```

If you have a PRODUCT entry for Enterprise COBOL for z/OS, ID(5655-EC6) in parmli member IFAPRDxx, then remove this entry.

When generating SMF records, the compiler will check the IFAPRDxx entry to see which version of the product is registered with the system - the Value Unit Edition version (5697-V61), or the Monthly License Charge version (5655-EC6). If the compiler finds an MLC entry (5655-EC6), or no entry for either product, it will generate SMF89 records for the MLC version. If the compiler finds a VUE entry only, it will generate SMF89 records for the VUE version.

6.2.2 Running Enterprise COBOL VUE from Unix System Services

If you mount the file system in which you have installed Enterprise COBOL VUE in read-only mode during execution, then you do not have to take further actions to activate Enterprise COBOL VUE. See 6.1.9, “Allocate, create and mount ZFS Files (Optional)” on page 22 for more information on the file system for Enterprise COBOL VUE.

6.2.3 Product Customization

The publication *IBM Enterprise COBOL for z/OS Customization Guide* (SC27-8712-03) contains the necessary information to customize and use Enterprise COBOL VUE.

The `/usr/lpp/IBM/cobol/igyv6r4/bin/cob2` is a shell script. If you put it in a location other than the default Enterprise COBOL File System Path `/usr/lpp/IBM/cobol/igyv6r4`, then change the environment variable `COBOL_INSTALL_DIR` as needed.

7.0 Converting from Enterprise COBOL to Enterprise COBOL Value Unit Edition

If you already have Enterprise COBOL for z/OS V6.4 installed on your system and you want to convert to Enterprise COBOL Value Unit Edition for z/OS V6.4, there is no need to reinstall the product. Enterprise COBOL VUE is the same as Enterprise COBOL made available under a different Product Identifier and pricing metric. To convert to Enterprise COBOL VUE, see section 6.2.1, “Product Registration for Subcapacity Reporting Tool” on page 26 for details on registering the product so that the correct SMF records are generated for subcapacity reporting.

8.0 Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

APAR numbers are provided in this document to assist in locating PTFs that may be required. Ongoing problem reporting may result in additional APARs being created. Therefore, the APAR lists in this document may not be complete. To obtain current service recommendations and to identify current product service requirements, always contact the IBM Customer Support Center or use S/390 SoftwareXcel to obtain the current "PSP Bucket".

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, New York 10504-1785
USA

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing
Legal and Intellectual Property Law
IBM Japan, Ltd.
19-21, Nihonbashi-Hakozakicho, Chuo-ku
Tokyo 103-8510, Japan

8.1 Trademarks

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at "Copyright and trademark information" at www.ibm.com/legal/copytrade.shtml.

Reader's Comments

Program Directory for IBM Enterprise COBOL VUE for z/OS, May 2022

We appreciate your input on this publication. Feel free to comment on the clarity, accuracy, and completeness of the information or give us any other feedback that you might have.

Use one of the following methods to send us your comments:

1. Send an email to comments@us.ibm.com

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

IBM or any other organizations will only use the personal information that you supply to contact you about the issues that you submit.

Thank you for your participation.



Printed in USA

G113-4529-03

