

*IBM SPSS Amos Installation Instructions
(Authorized User License)*



Contents

- Chapter 1. Installation instructions..... 1**
- System requirements.....1
- Authorization code..... 1
- Installing.....1
- Installing from a downloaded file..... 1
- Installing from the ISO file 1
- Notes for installation..... 1
- Licensing your product.....2
- Using the license authorization wizard 2
- Enabling for temporary usage..... 2
- Viewing your license..... 3
- Applying fix packs..... 3
- Uninstalling.....3
- Updating, modifying, and renewing IBM SPSS Amos 3

Chapter 1. Installation instructions

The following instructions are for installing IBM® SPSS® Amos version 32 using the license type authorized user license. This document is for users who are installing on their desktop computers.

Note: You cannot run IBM SPSS Amos remotely via Windows Terminal Services or Citrix with an authorized user license.

System requirements

To view the system requirements for IBM SPSS Amos, go to <https://www.ibm.com/software/reports/compatibility/clarity/softwareReqsForProduct.html>.

Authorization code

The authorization code is required when you install IBM SPSS Statistics. Entering the authorization code facilitates the license creation process.

See [Getting Started with Installation and Licensing for IBM SPSS Statistics](#) for details on the difference between an authorization and a license.

Check the instructions you received for obtaining your authorization code. If you cannot find your authorization code see [Creating your SPSS authorization code through the IBM SPSS License Key Center](#).

You should have received separate instructions for obtaining your authorization code. If you cannot find your authorization code, contact Customer Service by visiting .

Installing

Important: To install, you must be logged on to your computer with administrator privileges.

Installing from a downloaded file

You must run the installer as administrator:

1. Double-click the file that you downloaded and extract all the files to some location on your computer.
2. Using Windows Explorer, browse to the location where you extracted the files.
3. Right-click *setup.exe* and choose **Run as Administrator**.
4. Follow the instructions that appear on the screen.

Installing from the ISO file

You must have administrator privileges:

1. Using Windows Explorer, browse to the location where you downloaded the .iso file and double-click the file to mount it.
2. Right-click the newly mounted DVD drive and select **Install or run a program from your media**.
3. On the AutoPlay menu, click the item that you want to install, and then follow the instructions that appear on the screen.

Notes for installation

This section contains special instructions for this installation.

License type. Be sure to select authorized user license.

Licensing your product

After the main part of the installation is complete, click **OK** to launch the License Authorization Wizard. The License Authorization Wizard allows you to obtain a license for IBM SPSS Amos.

If you do not get a license now, you can enable IBM SPSS Amos to be used for a temporary usage period. After the temporary usage period has completed—and which begins when the product is first used—IBM SPSS Amos will no longer run. Therefore, it is recommended that you obtain a license as soon as possible. You must either obtain a license or enable for temporary usage to use IBM SPSS Amos.

Note: Licenses are tied to your computer's hardware with a **lock code**. If you replace your computer or its hardware, you will have a new lock code and will need to repeat the authorization process. This is also true if you re-image your computer. If you find out that you exceeded the allowable number of authorizations specified in the license agreement, go to to contact the Client Care team for assistance.

Important: The license is sensitive to time changes. If you must change the system time and then cannot run the product, contact the Client Care team for assistance by visiting .

Using the license authorization wizard

Note: You might be prompted for administrator credentials. Without the correct credentials, you will not be able to run the License Authorization Wizard.

1. If you don't launch the License Authorization Wizard during installation or cancel the License Authorization Wizard before obtaining a license, you can launch it by choosing **License Authorization Wizard** in the Windows Start menu program group for IBM SPSS Amos. You must run as administrator. Right-click the **License Authorization Wizard** shortcut and choose **Run As Administrator**.
2. When prompted, choose **License my product now**. If you want to enable for temporary usage instead, refer to [“Enabling for temporary usage” on page 2](#) .
3. When prompted, enter one or more authorization codes.

You should have received separate instructions for obtaining your authorization code. If you cannot find your authorization code, contact Customer Service by visiting .

The License Authorization Wizard sends your authorization code over the Internet to IBM Corp. and automatically retrieves your license. If your computer is behind a proxy, click **Configure proxy settings** and enter the appropriate settings.

If the authorization process fails, you will be prompted to send an e-mail message. Choose whether you want to send the e-mail message through your desktop e-mail program or through a Web-based e-mail application.

- If you choose the desktop option, a new message with the appropriate information will be created automatically.
- If you choose the Web-based option, you must first create a new message in your Web-based e-mail program. Then copy the message text from the License Authorization Wizard and paste it into your e-mail application.

Send the e-mail message and respond to the prompt in the License Authorization Wizard. The e-mail message will be processed almost instantaneously. You can click **Enter License Code(s)** to enter any license code(s) that you receive. If you already closed the License Authorization Wizard, restart it and select **License my product now**. On the Enter Codes panel, add the license code that you received and click **Next** to complete the process.

Enabling for temporary usage

You can enable for temporary usage instead of installing the regular license.

1. Launch the License Authorization Wizard.
2. When prompted, choose **Enable for temporary usage**.

3. On the next screen, click the browse button to locate the temporary usage file in the product installation directory (typically *temp.txt*).

Viewing your license

You can view the license by relaunching the License Authorization Wizard. The first panel displays the licensing information. Click **Cancel** when done, and click **Yes** when prompted about canceling.

Applying fix packs

To ensure problem-free operation, keep your product at the latest fix pack level. Complete all of the necessary pre-installation and post-installation tasks as described in the fix pack instructions.

Uninstalling

To completely uninstall IBM SPSS Amos:

1. Use the Windows Control Panel to remove IBM SPSS Amos.

Updating, modifying, and renewing IBM SPSS Amos

If you renew your license, you will receive a new authorization code (or codes).

